

**Table A1.6** Illustrative Module DEscription DIC

Variable Count	Dictionary Description	Dictionary Name		Privilege								
29	Module Properties	Module		0								
Parameter	Description	Dimension	Primary Key	Data Type	Scalar	Min	Max	Measure	Units	Stochastic	Preposition	Index 1
Class	Module class type	0	FALSE	STRING	TRUE	0	8			FALSE		
ConSchemeDic	Consumed dictionary names	2	FALSE	STRING	FALSE	1	4			FALSE		Scheme
Description	Module description lines	1	FALSE	STRING	FALSE	0	1024			FALSE		
Dictionary	Id(name) and path of input dictionary	0	FALSE	STRING	TRUE	0	512			FALSE		
Icon	Name and path of display icon	0	FALSE	STRING	TRUE	0	512			FALSE		
Login	Login for model server	0	FALSE	STRING	TRUE	0	32			FALSE		
ModelCmdLine	Model command line switches	0	FALSE	STRING	TRUE	0	64			FALSE		
ModelExe	Name and path of Model executable	0	FALSE	STRING	TRUE	0	512			FALSE		
ModelURL	Remote model server URL	0	FALSE	STRING	TRUE	0	512			FALSE		
Name	Module name	0	FALSE	STRING	TRUE	0	512			FALSE		
Password	Password for model server	0	FALSE	STRING	TRUE	0	32			FALSE		
PCCAddress1	Point of contact first address	0	FALSE	STRING	TRUE	0	64			FALSE		
PCCAddress2	Point of contact second address	0	FALSE	STRING	TRUE	0	64			FALSE		
PCCCity	Point of contact city	0	FALSE	STRING	TRUE	0	32			FALSE		
PCCCompany	Point of contact company name	0	FALSE	STRING	TRUE	0	64			FALSE		
PCCCountry	Point of contact country	0	FALSE	STRING	TRUE	0	32			FALSE		
PCCEmail	Point of contact email address	0	FALSE	STRING	TRUE	0	64			FALSE		
PCCFax	Point of contact fax telephone number	0	FALSE	STRING	TRUE	0	16			FALSE		
PCCPerson	Point of contact person	0	FALSE	STRING	TRUE	0	64			FALSE		
PCCPhone	Point of contact telephone number	0	FALSE	STRING	TRUE	0	16			FALSE		
PCCState	Point of contact state	0	FALSE	STRING	TRUE	0	16			FALSE		
PCCUrl	Point of contact web address	0	FALSE	STRING	TRUE	0	512			FALSE		
PCCZip	Point of contact zip code	0	FALSE	STRING	TRUE	0	16			FALSE		
ProSchemeDic	Produced dictionary names	2	FALSE	STRING	FALSE	1	4			FALSE		Scheme
Reference	Module reference lines	1	FALSE	STRING	FALSE	1	1024			FALSE		
Scheme	The name of a connection scheme	1	FALSE	STRING	FALSE	1	32			FALSE		
UICmdLine	UI command line switches	0	FALSE	STRING	TRUE	0	64			FALSE		
UIExe	Name and path of UI executable	0	FALSE	STRING	TRUE	0	512			FALSE		
Version	Module version description	0	FALSE	STRING	TRUE	0	32			FALSE		